







## CHANGING THE DIMENSION EDIT TO DOUBLE CLICK IN AUTOCAD ARCHITECTURE 2008

1. Type **CUI** on the command line to bring up the Customization Dialog.
2.  Look for the Double Click Actions category.  
But you don't see the Dimension listed!
3.  Switch to the **Transfer** tab.
4.  In the right panel, select **Open**.
5.  Browse to the *Support* folder under Documents and Settings.  
If you don't see it, you need to change your Explorer options to view hidden folders.  
If you can't find your cui files, run a **Search** using Explorer.



To change your view settings in Explorer, go to **Tools**→**Folder Options**.




Select the **View** tab.

Enable **Show hidden files and folders**.

Press **OK**.


6.



Locate the *acad.CUI* file.


Press **Open**.

7.



You should see the ADT.cui in the left pane and the acad.cui in the right pane.


8.



If you expand the Double Click Actions in the right pane, you will see Dimension.


Drag and drop the Dimension over to the left side under the Double Click Actions.

9.



Drag and drop the Dimension over to the left side under the Double Click Actions.

10.



Locate **Text, Edit** in the Command List.

11.



Drag and drop the Text, Edit command under the Dimension double click category.

12. Press **Apply**.

13.  Press **Save**.

14. Press **OK**.

Now when you double click on a dimension, the MTEXT edit window will come up instead of the Properties window.